


**Question :** How do I activate the F11 function in VisionPlus on AutoCad?

**Answer :**


**Warning :** This function is only available in AutoCad 2006 or higher.

Here is how you deactivate the F11 function in AutoCad so you can use the F11 (^++) of VisionPlus.


You must go in **Tools/Customize/Interface ...**



Then, from the **Customizations in ALL CUI Files** section, select **Keyboard Shortcuts -->Temporary Override Keys**.



Then, from the same section, select **Toggles Object Snap Tracking Mode**.  
From the *Properties* section, select **Shortcut** → **Key(s)**.



Press the "..." button from the **Key(s)** item.  
A window opens to reassign a new shortcut key.  
Enter the new shortcut key and press **OK**.



It is possible that F11 is already used by another command. Check in the **Keyboard Shortcuts** list which command is using it and reassign another key to it.